Contour moment

Moment functions are widely used in image analysis, such as pattern recognition, target classification, target recognition and orientation estimation, image encoding and reconstruction, etc. The moment set calculated from an image can not only describe the global characteristics of the image shape, but also provide a large amount of different geometric feature information about the image, such as size, position, direction and shape. The description ability of image moments is widely used in target recognition and orientation estimation in various fields of image processing, computer vision and robotics.

First moment: related to shape;

Second moment: shows how much the curve extends around the mean of the straight line;

Third-order moment: a symmetry measurement about the mean value; 7 invariant moments can be derived from the second-order moment and the third-order moment. The invariant moment is a statistical characteristic of the image, which satisfies the invariance of translation, expansion and contraction, and rotation, and is widely used in the field of image recognition.

1. Use

Code path: ~/yahboomcar_ws/src/opencv_apps/launch

• Start the camera

roslaunch yahboomcar_visual opencv_apps.launch img_flip:=false

• img_flip parameter: whether the image needs to be flipped horizontally, the default is false.

The [usb_cam-test.launch] file opens the [web_video_server] node by default, and you can directly use the [IP:8080] web page to view images in real time.

• Start the corner detection function of Opencv_apps

roslaunch opencv_apps contour_moments.launch # Contour moment

The debug_view for some functions is disabled, and there is no screen appearing. You can view the effect in the following two ways.

The reason for closing debug_view is that it will generate errors on the terminal, but the actual effect has not been affected.

Local View Screen

Enter the following command to select the corresponding topic

rqt_image_view

LAN viewing screen

Enter IP+port in the browser, for example:

2. Effect display

Contour moments use parameters. There will be a topic for subscribing images and publishing images.

| Parameter | Туре | Default | Analyze |
|----------------------|------|---------|---|
| ~use_camera_info | bool | true | Subscribe to the topic [camera_info] to get the default coordinate system ID, otherwise use the image information directly. |
| ~debug_view | bool | false | Whether to create a window to display the node image |
| ~canny_low_threshold | int | 0 | Canny edge detection low threshold |
| ~queue_size | int | 3 | Queue size |

Effect picture:

